

DSM2 Bay-Delta Tutorial 2: Source Tracking (Fingerprinting)

Purpose: The purpose of this tutorial is to use the source tracking capabilities of the model to create a fingerprinting study. We will set up both volumetric and concentration-based fingerprinting and visualize the results.

1. Reopen the historical tutorial

- a. In windows, navigate to `\{DSM2_home\}\tutorial\historical`. (folders and files are copied as described in the Delta tutorial 1)

2. Create a model for source tracking:

In the background, source tracking imposes a computational cost on QUAL that is the same as one additional constituent per source. For this reason, it is useful to comment out source tracking as a standard course of running DSM2. But when you desire source tracking, you can uncomment it as follows:

- a. In *historical_qual_ec.inp*, locate the GROUPS include section.
- b. Uncomment the group definitions for source tracking (delete the # sign at the start of the line). You may wish to review the referenced file to see how the groups are identified.
- c. Similarly uncomment the two fingerprinting files – the ones that have “source_track” in their names.

3. Define volumetric inputs

- a. Create the QUAL volumetric input file. Copy *historical_qual_ec.inp* and rename as *historical_qual_vol.inp*.
- b. Modify the concentration blocks. Go through each of the node and reservoir concentration files for QUAL ec. Modify the constituent (variable) to *unit*, value (FILE) to constant, (PATH) to 100. This step is conceptually simple, but will produce a large file – feel free to break it into several files if you prefer. If you are using Notepad++, you may want to use its column delete/copying features (press alt while you make your selection).

- c. Compare what you produced to the existing files in `common_input` that have “volumetric” in their names (node and reservoir concentration). Are they the same input? How could you test this using the echoed output?

4. Define the fingerprinting output

- a. Specify Clifton Court concentration output for each of the source groups defined in the previous step, for both constituents: *ec* and *unit*, in block `OUTPUT_RESERVOIR_SOURCE_TRACK`. The name should be `clifton_court`, the concentration (variable) should be `ec` or `volume` and the interval should be `1day`. Avoid redundancy or use of the source in the output name: i.e. use “`clifton_court`” for the name, not “`clifton_ag`” or “`clifton_ec`”. Because the source information is recorded in the F part of output `dss` file.
- b. Similar specification could be defined for channel source track in block `OUTPUT_CHANNEL_SOURCE_TRACK`. Pick any channel you are interested and do the definition.

5. Run HYDRO and QUAL for One Year

- a. Using *historical_hydro.inp*, *historical_qual_ec.inp*, *historical_qual_vol.inp* as the launch files, run HYDRO and QUAL for one year in 2002. Start QUAL a day later to avoid mass conservation errors in the first hour. Make sure the `init_conc` variable (in SCALAR block) is set to zero so that there will be no initial condition contribution for any variables (note: for a volumetric fingerprint, it may be useful to make this concentration 100 if you want to include initial conditions in the fingerprint analysis).
- b. Open the output file (*historical.dss*), and examine the results.

6. Process the output

- a. Use VISTA or HEC-DSSVUE to open up the output file. Copy May-September concentrations source track of Clifton Court for each location. Paste the output into a new sheet in the Excel provided called `excel_fingerprint.xls`, which you can

use as a reference. Use the “stacked area plot” in Excel (one of the standard Excel plot types) to plot up the fingerprint results.